kmerExtractor

Release 1.0

Camila Riccio-Rengifo, Mauricio Peñuela, Jorge Finke, Camilo Rocha

CONTENTS:

1	Documentation	3					
	kmerExtractor module	3					
2	kmerExtractor user manual	7					
	2.1 Import libraries	7					
	2.2 Compute k-mers	7					
	2.3 Read k-mer files if already computed	9					
	2.4 Group all windows within each chromosome	9					
	2.5 Group all chromosomes	10					
	2.6 k-mer figures	11					
3	Indices and tables						
Ру	non Module Index	19					
In	ex	21					

A genome sequence is composed of four basic types of nucleotides: adenine (A), cytosine (C), guanine (G), and thymine (T). All possible nucleotide substrings of length k are called **k-mers**. For example, for k=2 there are $4^k=4^2=16$ different 2-mers corresponding to: AA, AC, AG, AT, CA, CC, CG, CT, GA, GC, GG, GT, TA, TC, TG, TT.

The kmerExtractor software calculates the k-mer frequencies for windows within the chromosomes of an organism's sequence. It takes as input a FASTA file with the nucleotide sequence of an organism separated by chromosomes. The software splits the chromosomes into windows of the size specified by the user. For a given k, the kmerExtractor computes the frequency of the k-mers in the different windows within the chromosomes. It returns a csv file indicating the chromosome, the window index, the start and end position of the window, and the frequencies of the corresponding k-mers.

CONTENTS: 1

2 CONTENTS:

DOCUMENTATION

1.1 kmerExtractor module

kmerExtractor.**CGR**(sequence, d=1)

Generate the X and Y coordinates of the Chaos Game Representation (CGR) for the input sequence. Purine nucleotides (A and G) are placed on the minor diagonal, and the pyrimidine nucleotides (C and T) on the main diagonal. The CGR is built in a square of dimensions $2d \times 2d$ with center at the coordinates (0,0). Only the four basic uppercase nucleotides (A, C, G, T) are accepted. Any other character is ignored.

Parameters

- **sequence** (*str*) Nucleotide sequence.
- **d** (*int*) Half of the side of the square. Default to 1.

Returns The x and y coordinates of the CGR.

Return type tuple[list[float],list[float]]

kmerExtractor.FCGR(kmers)

Organize the k-mers and their associated values in the common structure of Frequency Chaos Game Representation (FCGR), i.e., a matrix of dimensions N x N, where $N = 4^{(k/2)}$; with the upper left corner equal to the k-mer of C, the upper right corner the k-mer of G, the lower left corner the k-mer of A, and the lower right corner the k-mer of T.

Parameters kmers (*dict*) – dictionary mapping the k-mers to a real value. All k-mers must be of the same length.

Returns FCGR matrix and the names of the k-mers in the matrix.

Return type tuple[numpy.ndarray, numpy.ndarray]

kmerExtractor.kmers_by_window(filepath, k, window_size=100000, output_path=None)

Calculate the frequency of k-mers by windows within each of the chromosome sequences. First, the entire sequence contained within the FASTA file is read. The sequences of each chromosome are then identified and separated. Subsequently, each chromosome is separated into windows of the specified size. Finally, the frequencies of the k-mers are calculated for each window.

Parameters

- **filepath** (*str*) Location of the FASTA file containing the nucleotide sequence of an organism separated by chromosomes.
- **k** (*int*) Length of k-mers.
- window_size (int) Window size, in number of base pairs, to be used to count the frequency of k-mers within the chromosome. Must be less than or equal to the length of the smallest chromosome. Default to 100000.

• **output_path** (*str*) – Path to the directory where the output csv file will be saved. If not specified, the output file will be saved in the same directory as the input file. Default to None

Returns Dataframe indicating the chromosome, the window index, the start and end positions of the window, and the frequencies of the corresponding k-mers.

Return type pandas.DataFrame

kmerExtractor.kmers_by_window_opt(filepath, k, window_size=100000, output_path=None)

Calculate the frequency of k-mers by windows within each of the chromosome sequences. It calculates the k-mers, as it reads the FASTA file, optimizing space by avoiding storing the sequence.

Parameters

- **filepath** (*str*) Location of the FASTA file containing the nucleotide sequence of an organism separated by chromosomes.
- **k** (*int*) Length of k-mers.
- window_size (int) Window size, in number of base pairs, to be used to count the frequency of k-mers within the chromosome. Must be greater than the number of nucleotides per line in the input FASTA file. Default to 100000
- **output_path** (*str*) Path to the directory where the output csv file will be saved. If not specified, the output file will be saved in the same directory as the input file. Default to None

Returns Dataframe containing the k-mer frequencies for all windows of each chromosome.

Return type pandas.DataFrame

kmerExtractor.kmers_in_sequence(sequence, k)

Calculate the frequency of k-mers in a given sequence. Only k-mers containing the four basic uppercase nucleotides (A,C,G,T) are accepted. Any substrings of length k that have any other character in their composition will be disregarded and thus not considered as k-mers.

Parameters

- **sequence** (*str*) Nucleotide sequence.
- **k** (*int*) Length of k-mers.

Returns Dictionary containing the k-mer frequencies. Keys are the k-mers and values are the corresponding frequencies.

Return type dict

$kmerExtractor.plot_CGR(sequence, d=1, markersize=1, ax=None, figsize=(6, 6))$

Plot the Chaos Game Representation (CGR) of the input sequence. Purine nucleotides (A and G) are placed on the minor diagonal, and the pyrimidine nucleotides (C and T) on the main diagonal. The CGR is built in a square of dimensions 2d x 2d with center at the coordinates (0,0). Only the four basic uppercase nucleotides (A, C, G, T) are accepted. Any other character is ignored.

Parameters

- **sequence** (*str*) Nucleotide sequence.
- **d** (*int*) Half of the side of the square in which the CGR is built. Default to 1.

Returns The Axes object containing the plot.

Return type matplotlib.axes._axes.Axes

kmerExtractor.plot_FCGR(df, chromosome=None, window=None, figsize=(7, 6), colormap='bwr', ax=None)
Plot the Frequency Chaos Game Representation (FCGR) of the k-mers in the input dataframe.

Parameters

- df (pandas.DataFrame) Dataframe with the k-mer frequencies by windows across chromosomes.
- **chromosome** (*str*) Name of the chromosome to plot. If None, parameter window must be None, plotting the sum of k-mers across all chromosomes. Default to None.
- window (int) Number of the window to plot. If None, plot the sum of all windows for each chromosome. Default to None.
- **figsize** (tuple[int,int]) The size in inches of the figure to create. Default to (7,6).
- **colormap** (*str*) Matplotlib colormap name. The mapping from data values to color space. Default to 'bwr'.
- ax (matplotlib.axes.Axes) Axes in which to draw the plot, otherwise use the currently-active Axes. Default to None.

Returns The Axes object containing the plot.

Return type matplotlib.axes._axes.Axes

kmerExtractor.plot_kmers_across_windows(df, kmer_names, chromosome, figsize=(12, 4), ax=None)
Plot the frequencies of the given k-mers across the windows of a given chromosome.

Parameters

- **df** (pandas.DataFrame) dataframe with the k-mer frequencies by window.
- **kmer_names** (*list*) list of k-mer names to plot.
- **chromosome** (*str*) name of the chromosome to plot.
- **figsize** (tuple[int,int]) The size in inches of the figure to create. default to (12,4).
- ax (matplotlib.axes._axes.Axes) The Axes object containing the plot. If None, a new figure and axes is created. Default to None.

Returns The Axes object containing the plot.

Return type matplotlib.axes._axes.Axes

 $kmerExtractor.plot_kmers_freq_within_chromosomes(df, figsize=(15, 6), ax=None)$

Plot the sum of the k-mer frequencies within each chromosome.

Parameters

- **df** (pandas.DataFrame) dataframe with the k-mer frequencies by window.
- **figsize** (tuple[int,int]) The size in inches of the figure to create. default to (15,6).
- ax (matplotlib.axes.Axes) Axes in which to draw the plot, otherwise use the currently-active Axes. Default to None.

Returns The Axes object containing the plot.

Return type matplotlib.axes._axes.Axes

CHAPTER

TWO

KMEREXTRACTOR USER MANUAL

Below we present examples of how to use the main functions of the software.

2.1 Import libraries

```
[1]: import pandas as pd
import matplotlib.pyplot as plt

# software to extract the k-mers
import kmerExtractor as kex
```

2.2 Compute k-mers

Specify the corresponding directory of the FASTA files from which you want to extract the k-mers, and the directory where you want to save the output files. Also define the window size (in base pairs) for which you want the frequency of k-mers to be counted.

In this case we will use the genome of arabidospsis, tomato and maize, with a window size of 100000 bp for all genomes.

```
[2]: filepath_ara = '../input_data/arabidopsis_genome.fasta'
filepath_tom = '../input_data/tomato_genome.fasta'
filepath_mz = '../input_data/maize_genome.fasta'
output_path = '../output_data'
window_size = 100_000
```

Now use the kmers_by_window_opt function to calculate the k-mers of each genome for the k of your choice.

In the output file, the first column indicates the chromosome, the second column the window index, the third and fourth columns indicate the start and end position of the window respectively, and the rest of the 4^k columns correspond to the k-mer frequencies. This data is saved in a csv file and stored in a dataframe for downstream analysis within the tutorial.

The resulting dataframe for arabidopsis 2-mers looks like shown below.

(continued from previous page)

```
df_2mers_mz = kex.kmers_by_window_opt(filepath_mz, k=2, window_size=window_size,_
     →output_path=output_path)
     df_2mers_ara
     100%|| 1537509/1537509 [00:45<00:00, 33733.02it/s]
     100%|| 10090326/10090326 [04:45<00:00, 35388.84it/s]
     100%|| 25502007/25502007 [12:31<00:00, 33940.82it/s]
[3]:
          chromosome
                        window
                                    start
                                                  end
                                                           AA
                                                                 AC
                                                                        AG
                                                                               ΑT
                                                                                     CA
                                                                                         \
                                                               5201
                                                                      5956
                                                                            9480
                 chr1
                             0
                                         1
                                              100000
                                                       11617
                                                                                   6269
                                   100001
                                                               5241
                                              200000
                                                       10857
                                                                      5871
                                                                                   6080
     1
                 chr1
                             1
                                                                            8727
     2
                             2
                                   200001
                                                       10623
                                                               5144
                 chr1
                                              300000
                                                                      6129
                                                                            8658
                                                                                   6350
     3
                 chr1
                             3
                                   300001
                                              400000
                                                        9548
                                                               5117
                                                                      6328
                                                                            7979
                                                                                   6483
     4
                 chr1
                             4
                                   400001
                                              500000
                                                       11515
                                                               5294
                                                                      5692
                                                                            9068
                                                                                   6225
                   . . .
                                                                . . .
                                                                       . . .
                                                                              . . .
     . . .
                           . . .
                                                          . . .
                                                                      5970
     1190
                                 26700001
                                            26800000
                                                       11432
                                                               5154
                                                                            9120
                 chr5
                           267
                                                                                   6440
     1191
                 chr5
                           268
                                 26800001
                                            26900000
                                                       11549
                                                               5299
                                                                      5782
                                                                            9116
                                                                                   6113
     1192
                           269
                                 26900001
                                                        8826
                                                               4001
                 chr5
                                            26975502
                                                                      4609
                                                                            6658
                                                                                   4719
     1193
                 chr5
                           269
                                 26900001
                                            26975502
                                                        8826
                                                               4001
                                                                      4609
                                                                            6658
                                                                                   4719
     1194
                 chr5
                           269
                                 26900001
                                            26975502
                                                        8826
                                                               4001
                                                                      4609
                                                                            6658
                                                                                   4719
              CC
                    CG
                           CT
                                                      GT
                                                             TA
                                                                    TC
                                  GA
                                         GC
                                               GG
                                                                          TG
                                                                                  TT
     0
            3277
                  2412
                         5588
                                6375
                                      2998
                                             3460
                                                    5248
                                                           7993
                                                                 6069
                                                                        6253
                                                                               11803
     1
            3516
                  2983
                         5895
                                6670
                                      3174
                                             3758
                                                    5578
                                                           7089
                                                                 6544
                                                                        6567
                                                                               11449
     2
            3575
                  2655
                         6386
                                6617
                                      3378
                                             3616
                                                    5325
                                                           6964
                                                                 6869
                                                                        6536
                                                                               11174
     3
                                                                        6759
            4297
                  2771
                         6834
                                6625
                                      3923
                                             4047
                                                    5310
                                                           6315
                                                                 7049
                                                                               10614
     4
            3578
                  2638
                         5896
                                6455
                                      3027
                                             3592
                                                    5271
                                                           7375
                                                                 6438
                                                                        6422
                                                                               11513
            3528
                  2620
                         5942
                                6521
                                      3051
                                             3289
                                                    5280
                                                           7283
                                                                 6797
                                                                        6262
     1190
                                                                               11310
     1191
            3457
                  2948
                         5881
                                6405
                                      3068
                                             3254
                                                    5222
                                                           7680
                                                                 6575
                                                                        5965
                                                                               11685
     1192
            2639
                  2158
                         4387
                                5163
                                      2352
                                             2573
                                                    3979
                                                           5386
                                                                 4912
                                                                        4726
                                                                                8413
                                                           5386
                                                                 4913
                                                                        4726
     1193
            2639
                  2158
                         4387
                                5163
                                      2352
                                             2573
                                                    3979
                                                                                8413
     1194
            2639
                  2158
                         4387
                                5163
                                      2352
                                             2573
                                                    3979
                                                           5386
                                                                 4914
                                                                        4726
                                                                                8413
     [1195 rows x 20 columns]
```

However, a most natural approach is to use k = 3, since the 3-mers represent codons, which encode for amino acids or signal the termination of protein synthesis (stop signals).

The resulting dataframe for arabidopsis 3-mers looks like below.

```
[4]: df_3mers_ara = kex.kmers_by_window_opt(filepath_ara,k=3,window_size=window_size,output_
     →path=output_path)
    df_3mers_tom = kex.kmers_by_window_opt(filepath_tom,k=3,window_size=window_size,output_
     →path=output_path)
    df_3mers_mz = kex.kmers_by_window_opt(filepath_mz,k=3,window_size=window_size,output_
     →path=output_path)
    df_3mers_ara
     100%|| 1537509/1537509 [00:54<00:00, 28160.74it/s]
     100%|| 10090326/10090326 [05:59<00:00, 28039.88it/s]
     100%|| 25502007/25502007 [15:53<00:00, 26741.24it/s]
[4]:
          chromosome
                      window
                                 start
                                              end
                                                    AAA
                                                          AAC
                                                                AAG
                                                                      AAT
                                                                             ACA
    0
                chr1
                           0
                                     1
                                           100000
                                                   4415
                                                         1966
                                                               2228
                                                                     3008
                                                                           1926
```

(continues on next page)

(continued from previous page) chr1 chr1 chr1 chr1 chr5 chr5 chr5 chr5 chr5 ACC TCG TCT TGA TGC TGG TGT TTA TTC TTG TTT [1195 rows x 68 columns]

2.3 Read k-mer files if already computed

Calculating k-mers can take longer for larger genomes. That's why you also have the option to load previously saved files, so you don't have to recalculate the k-mers every time you want to plot some figures or do further analysis.

```
[5]: df_2mers_ara = pd.read_csv(output_path +'/CGRW_k2_arabidopsis_genome.csv')
    df_2mers_tom = pd.read_csv(output_path +'/CGRW_k2_tomato_genome.csv')
    df_2mers_mz = pd.read_csv(output_path +'/CGRW_k2_maize_genome.csv')

df_3mers_ara = pd.read_csv(output_path +'/CGRW_k3_arabidopsis_genome.csv')
    df_3mers_tom = pd.read_csv(output_path +'/CGRW_k3_tomato_genome.csv')
    df_3mers_mz = pd.read_csv(output_path +'/CGRW_k3_maize_genome.csv')
```

2.4 Group all windows within each chromosome

If you don't want the k-mer frequencies by windows within the chromosomes, you can get the cumulative frequencies for each chromosome as shown in the cell below. For example, the resulting dataframe for arabidopsis would have only 5 rows corresponding to its 5 chromosomes.

(continued from previous page)

```
df_2mers_mz_bychr = df_2mers_mz.groupby('chromosome').agg({k:'sum' for k in df_2mers_mz.
     \hookrightarrow columns[4:]})
     df_2mers_ara_bychr
                                AC
                                          AG
                                                   ΑT
                                                             CA
                                                                       CC
                                                                               CG \
[6]:
                       AA
     chromosome
                           1588202
                                    1794811
                                              2806911
                                                       1923811
                                                                 1016038
                                                                           697362
     chr1
                 3519572
     chr2
                           1029105
                                    1160640
                                              1834416
                                                       1246754
                                                                  672290
                                                                           457569
                 2291405
     chr3
                 2697289
                           1228414
                                    1405644
                                              2153303
                                                        1498561
                                                                  804334
                                                                           559027
                            980389
                                    1109010
                                              1707158
                                                                  637226
                                                                           439583
     chr4
                 2143926
                                                        1184064
     chr5
                 3140913
                          1410681
                                    1608073
                                              2510382
                                                       1712226
                                                                  907201
                                                                           634608
                       CT
                                         GC
                                                  GG
                                                            GT
                                                                     TA
                                                                               TC
                                GA
     chromosome
     chr1
                 1798090
                           1930160
                                    902322
                                             1008839
                                                      1579754
                                                                2335983
                                                                          1928721
     chr2
                 1166315
                           1249456
                                    584680
                                              660355
                                                       1026228
                                                                1527955
                                    714668
     chr3
                 1396347
                           1516501
                                              805341
                                                       1226134
                                                                1772296
                                                                          1510857
     chr4
                 1110444
                           1195069
                                    560350
                                              630128
                                                        970513
                                                                1417419
                                                                          1193357
                 1605965
                                                                2075592 1733770
     chr5
                           1741333
                                    808346
                                              914520
                                                      1422652
                       TG
                                TT
     chromosome
                          3512205
     chr1
                 1920061
     chr2
                 1242154
                          2289303
     chr3
                 1492635
                           2672182
     chr4
                 1177332
                           2125863
     chr5
                 1729636 3160014
```

2.5 Group all chromosomes

Furthermore, you can pool the k-mer frequencies of all the chromosomes and have the cumulative counts of the entire sequence.

```
[7]: df_2mers_all = pd.DataFrame()
     df_2mers_all['arabidopsis'] = df_2mers_ara_bychr.sum()
     df_2mers_all['tomato'] = df_2mers_tom_bychr.sum()
     df_2mers_all['maize'] = df_2mers_mz_bychr.sum()
     df_2mers_all.T
                                                                        CA
                                                                                    CC \
[7]:
                          AA
                                     AC
                                                 AG
                                                             AT
     arabidopsis
                   13793105
                                6236791
                                            7078178
                                                      11012170
                                                                   7565416
                                                                               4037089
                                           41002572
     tomato
                   85677817
                               37700236
                                                      75901364
                                                                  45946447
                                                                              25138712
     maize
                   161563751
                              108257047
                                          128688710
                                                     136989307
                                                                 133796230
                                                                             120957040
                         CG
                                    CT
                                                GA
                                                            GC
                                                                       GG
                                                                                   GT
                   2788149
                               7077161
                                           7632519
                                                      3570366
     arabidopsis
                                                                  4019183
                                                                              6225281
     tomato
                   11804902
                              40969026
                                          42920385
                                                     18121904
                                                                 25183170
                                                                             37739813
                             128781627
                                         129723428
                                                    112442579
                                                                121098322
     maize
                  87977339
                                                                            108465666
                          TA
                                     TC
                                                 TG
     arabidopsis
                     9129245
                                7623563
                                            7561818
                                                      13759567
```

(continues on next page)


(continued from previous page)

tomato	65737185	42898271	45974544	85737480
aize	110415392	129855155	133966157	161938133

2.6 k-mer figures

2.6.1 Plot k-mers across windows

With the plot_kmers_across_windows function you can plot the frequencies of the k-mers of your choice across the windows of a specified chromosome.




You can also use this function to compare, placing the plot of different chromosomes on different axes within the same figure.

```
[9]: fig,ax = plt.subplots(2,1,figsize=(12,10),gridspec_kw={'hspace': 0.3})

kex.plot_kmers_across_windows(df_3mers_ara,['TTT','CCC'],'chr1',ax=ax[0])
kex.plot_kmers_across_windows(df_3mers_ara,['TTT','CCC'],'chr4',ax=ax[1])

plt.show()
```


2.6. k-mer figures




2.6.2 Plot k-mer frequencies within each chromosome

The plot_kmers_freq_within_chromosomes function makes a stacked bar graph of the frequency of different kmers per chromosome. For the same k-mer, each stacked bar represents a different chromosome of the corresponding color.

[10]: b = kex.plot_kmers_freq_within_chromosomes(df_2mers_ara, figsize=(8,4))






2.6.3 Plot FCGR structure

The technique to show the k-mer frequencies as images is known as Frequency Chaos Game Representation (FCGR). It corresponds to a matrix of dimensions $2^k \times 2^k$; with the upper left corner equal to the k-mer of C, the upper right corner the k-mer of G, the lower left corner the k-mer of A, and the lower right corner the k-mer of T.


The plot_FCGR function plots the FCGR of a sequence as a heatmap that allows to appreciate the relative frequencies of each k-mer. You can plot the FCGR for a specific chromosome and window, the cumulative frequency for an entire chromosome (if no window is specified), or the cumulative frequency for the entire genome (if neither chromosome nor window is specified).

[12]: d = kex.plot_FCGR(df_3mers_ara,'chr1',window=145)

2.6. k-mer figures



You can also adjust the size of the figure and the colormap to your preference as shown below




Aditionally, is possible compare the FCGR of multiple genomes as shown in the following cell

```
[14]: fig,ax = plt.subplots(1,3,figsize=(20,5))

kex.plot_FCGR(df_3mers_ara,ax=ax[0])
kex.plot_FCGR(df_3mers_tom,ax=ax[1])
kex.plot_FCGR(df_3mers_mz,ax=ax[2])

ax[0].set_title('Arabidopsis')
ax[1].set_title('Tomato')
ax[2].set_title('Maize')
plt.show()
```



2.6.4 Plot CGR

Finally, although it is not the main objective of the software, a function to generate the CGR image of a sequence is included. In the following example, the FASTA file of the Arabidopsis genome is read and the CGR of the first 100 kb is generated.

```
# Read FASTA file with complete genome separated by chromosomes
f_in = open(filepath_ara, 'r')
all_file = f_in.read()
f_in.close()


# join lines
seq_all = "".join(all_file.split("\n"))
del all_file

# Split sequence by chromosomes
seq_bychr = re.split('>chr[1-9]*', seq_all)[1:]
del seq_all

# plot CGR of the first chromosome, first window (first 100 Kb)
f = kex.plot_CGR(seq_bychr[0][:100_000],markersize=0.2)

100%|| 100000/100000 [00:00<00:00, 1886046.78it/s]</pre>
```

2.6. k-mer figures



CHAPTER

THREE

INDICES AND TABLES

- genindex
- modindex
- search

PYTHON MODULE INDEX

k

kmerExtractor, 3

20 Python Module Index

INDEX

```
C
CGR() (in module kmerExtractor), 3
F
{\tt FCGR()}\ (in\ module\ kmerExtractor),\, 3
K
kmerExtractor
    module, 3
kmers_by_window() (in module kmerExtractor), 3
kmers_by_window_opt() (in module kmerExtractor), 4
kmers_in_sequence() (in module kmerExtractor), 4
M
module
    kmerExtractor, 3
Р
plot_CGR() (in module kmerExtractor), 4
plot_FCGR() (in module kmerExtractor), 4
plot_kmers_across_windows() (in module kmerEx-
        tractor), 5
plot_kmers_freq_within_chromosomes() (in mod-
        ule kmerExtractor), 5
```